

# Network Share Persistence

For extra security against Ransomware or Malware attacks it may be desirable to ensure that backup targets on a NAS or a Windows shared folder are disconnected as soon as your backup has finished.

Please also see [Macrium Image Guardian](#) for more information on how the built-in functionality of MIG can help protect your backups on protected shares.

If necessary, Macrium Reflect will automatically create a network connection whenever a backup is created on a network share. Network connections persists until the number of seconds in the Windows network session 'time-out' value is reached. This value is Windows setting and defaults to 15 minutes. Since Windows doesn't share credentials and only one user can have an authenticated network access to a share at any one time, concurrent connections are not allowed by Windows networking.

More information from MS on time-outs and disconnects can be found by clicking [here](#).

## How to disconnect active shares

Run the following command in an [elevated command prompt](#):

```
net use /delete \\server\sharename
```

## How to change the idle timeout value for all network share connections

Run the following command in an [elevated command prompt](#):

```
net config server /autodisconnect:number
```

Where **number** is the idle timeout in seconds. Use **0** for very quick disconnections and **-1** to never disconnect.

## Macrium Reflect also has a way to automatically delete active connections

Authenticated Network connections created by Macrium Reflect at the start of a backup can be automatically terminated on application exit rather than waiting for the default Windows timeout.

To enable this, create the following registry entry:

Key:	HKEY_LOCAL_MACHINE\SOFTWARE\macrium\reflect\Settings
Name:	DeleteNetworkConnection
Type:	DWORD 32 bit
Value:	1

