


Adding iSCSI support to Windows PE

Macrium Reflect can include the components necessary to connect Windows PE to iSCSI. This enables restoration and clones to iSCSI connected disks.

1. Ensure that your Windows PE rescue media has been created with the **'Include optional components'** option selected.




2. Boot into Windows PE and start a command prompt.



The command line can be accessed by clicking the black icon on the bottom left corner of your screen.

3. You will need to change the IP address of your Windows Pre-installation Environment to the same IP address that is configured on your Windows Host in order to be authenticated by the iSCSI target since unknown IP addresses will result in a timeout when trying to login to the target.

Take **'Other Tasks' > 'Network Config'**



4. In Network Configuration input the same IP address that is configured to connect to the iSCSI target.
Note: In this case the Windows host IP address is '10.17.0.15'. Please replace with the correct IP address for your Windows host.

Network Configuration

Specify Network Address Settings

Contact your network administrator if auto assignment (DHCP) is not supported

Microsoft Hyper-V Network Adapter

Obtain an IP address automatically

Use the following IP address

IP address: 10 . 17 . 0 . 15

Subnet mask: 255 . 128 . 0 . 0

Gateway: 10 . 0 . 0 . 1

Specify DNS Settings

Obtain a DNS server automatically

Use the following DNS server address

Preferred DNS server: 10 . 0 . 0 . 1

Alternate DNS server: 255 . 255 . 255 . 255


5. In the command window type “**net start msiscsi**” to enable the Microsoft iSCSI server:

```
Administrator: X:\Windows\System32\cmd.exe
Microsoft Windows [Version 6.3.9600]

X:\Windows\system32>net start msiscsi
The Microsoft iSCSI Initiator Service service is starting.
The Microsoft iSCSI Initiator Service service was started successfully.

X:\Windows\system32>
```

6. After the service has started connect the iSCSI target to Windows PE by typing “**iscsictl QAddTargetPortal 10.17.0.32**”.
- Note:** In this case the target is '10.17.0.32' please replace with the correct IP address for your own iSCSI target.




```
Administrator: X:\Windows\System32\cmd.exe
X:\Windows\system32>iscsicli QAddTargetPortal 10.17.0.32
Microsoft iSCSI Initiator Version 6.3 Build 9600

The operation completed successfully.
X:\Windows\system32>
```

Note: Replace 10.17.0.32 with your IP address

7. Connect to the target in order to find out its Internet Qualified Name that is used to logon to the iSCSI target. Type: “**iscsicli ListTargets T**”




```
Administrator: X:\Windows\System32\cmd.exe
X:\Windows\system32>iscsicli ListTargets T
Microsoft iSCSI Initiator Version 6.3 Build 9600


Targets List:
    iqn.1991-05.com.microsoft:fileserver-iscsi-drive-target
The operation completed successfully.
X:\Windows\system32>
```

The above command gave output to a target name: **iqn.1991-05.com.microsoft:fileserver-iscsi-drive-target**
This target name is used to logon and access the iSCSI Virtual Disk.

8. Using the “**iscsicli QLoginTarget iqn.1991-05.com.microsoft:fileserver-iscsi-drive-target**” you will add the iSCSI Virtual Disk to Reflects interface and it will appear as a local disk available for restore and clone.



9. If the iSCSI disk is not visible at first in the restore tab, **select the 'Backup' tab** in Reflect and **click Refresh**.



Your iSCSI disk is now connected and can be used as a target for your image restores and clones.